

# Modifier l'adresse IP utilisé par Exim

Modifier l'adresse IP utilisé par Exim.

Peut-être utile si votre IP principale est sur une blacklist à cause d'un site compromis.



Assurez-vous que l'adresse IP qui sera utilisé aura une entrée RDNS (reverse DNS) valide.

## Modification du fichier de configuration `exim.conf`

Connectez-vous via la [console \(SSH\)](#) avec votre compte administrateur et passer en mode [root](#).

```
nano /etc/exim.conf
```

Trouver dans la configuration:

```
remote_smtp:  
  driver = smtp
```

Et ajouter la ligne suivante **sous** `remote_smtp::`

Remplacer `VOTRE_NOUVEAU_IP` par la nouvelle adresse IP utilisé par Exim pour l'envoi des e-mails.

```
interface = VOTRE_NOUVEAU_IP
```

Redémarrer Exim

```
systemctl restart exim
```

## Modification des entrées SPF

Remplacer `VOTRE_NOUVEAU_IP` par la nouvelle adresse IP utilisé par Exim pour l'envoi des e-mails.

```
cd /var/named  
mkdir /root/dbbackup  
cp *.db /root/dbbackup  
perl -pi -e 's/v=spf1.*$/v=spf1 a mx ip4:VOTRE_NOUVEAU_IP  
include:masterdomain.com -all"/ *.db
```

# Liens

- [I want to change the SPF records for all of my domains.](#)
- [Force exim to send email from a particular IP](#)

From:

<https://wiki.proletaire.net/> - **Wiki**

Permanent link:

[https://wiki.proletaire.net/email/exim/modifier\\_adresse\\_ip?rev=1586999179](https://wiki.proletaire.net/email/exim/modifier_adresse_ip?rev=1586999179)

Last update: **2020/04/16 01:06**

