

# Installation de Project Zomboid en tant que service

Fichier pour faire fonctionner Projet Zomboid en service avec SystemD

## **/etc/systemd/system/zomboid.service**

```
cat >/etc/systemd/system/zomboid.service <<'EOL'
[Unit]
Description=Project Zomboid Server
After=network.target
StartLimitIntervalSec=60
StartLimitBurst=10

[Service]
Restart=always
PrivateTmp=true
Type=simple
RemainAfterExit=yes
User=zserver
WorkingDirectory=/home/zserver/zomboid_server/
ExecStart=/bin/bash --login -c 'source /home/zserver/.bashrc; /bin/sh -c
"exec /home/zserver/zomboid_server/start-server.sh
</home/zserver/zomboid_server/zomboid.control"
ExecStop=/bin/bash --login -c 'source /home/zserver/.bashrc; /bin/sh -c
"echo save > /home/zserver/zomboid_server/zomboid.control; sleep 15; echo
quit > /home/zserver/zomboid_server/zomboid.control"
ExecStopPost=/bin/bash --login -c 'source /home/zserver/.bashrc; rm -rf
/home/zserver/zomboid_server/zomboid.control; killall -KILL
ProjectZomboid64; killall -KILL start-server.sh

Sockets=zomboid.socket
KillSignal=SIGCONT

[Install]
WantedBy=multi-user.target
EOL
```

## **/etc/systemd/system/zomboid.socket**

```
cat >/etc/systemd/system/zomboid.socket <<'EOL'
[Unit]
BindsTo=zomboid.service

[Socket]
ListenFIFO=/home/zserver/zomboid_server/zomboid.control
FileDescriptorName=control
RemoveOnStop=true
```

SocketMode=0660  
SocketUser=zserver

EOL

Lien:

- [https://pzwiki.net/wiki/Dedicated\\_server](https://pzwiki.net/wiki/Dedicated_server)

From:

<https://wiki.proletaire.net/> - **Wiki**

Permanent link:

<https://wiki.proletaire.net/zomboid/systemd?rev=1714947692>

Last update: **2024/05/05 22:21**

